



## Texturizer Instruction Sheet

### Straight Perm

**Preparation:** Wash hair with Washe Elite™ Shampoo and Condition with Resurrect™ for 3-5 minutes.\* Rinse well and towel dry.

**Mixing:** Using a glass or plastic bowl place one premeasured packet of Paul Brown™ Hawaiian Protein Flora Complex and add approximately 3 1/2 ounces of Paul Brown™ Straight Perm Solution and mix with the comb end of a rat tail comb until a creamy paste with no lumps forms. The paste should be just thick enough to not run off the comb. If it thickens simply apply a small amount of Straight Perm Solution and remix.

**Application:** Starting at the nape of the neck, take the first sub parting of approximately 1/2 inches and comb through to ensure no tangles. Take the comb end of the rat rail comb, pick up a reasonable amount of paste and apply the mixture to the scalp to both the top and underneath sides of the hair section. Using your hands and comb, gently work the paste through the hair making sure that all the hair is thoroughly covered with the mixture.

Lift and over direct the hair, placing the appropriate length Straight Perm Board under the section and placing the hair onto the board. Hold the board firmly against the scalp and using the teeth of the comb, comb the hair down on to the board. Then using the backside of the comb

ribbon and flatten the hair removing excess product.

Work from the scalp toward the ends in short segments, first straightening, then flattening. Make sure the board is firm against the comb and that it does not slip away while smoothing the hair. The hair should shine like a piece of glass. DO NOT over-comb the hair, as this can cause hair damage. Begin each new section at the bottom and continue upward. Keep hair damp and tangle-free with Paul Brown™ Treat Elite™ throughout the application.

**Processing:** *Normal, previously permed or color treated hair:* leave paste on hair for 30 minutes (minimum), begin timing from the last board or roller application. *Color-Treated Hair:* Mist section with Treat Elite prior to application and process for 30 minutes from the last board or roller application. *Naturally Curly or Wavy Hair:* Process for a full 30 minutes from the last board or roller application, then with a spray bottle containing STEP ONE re-moisten each board and process for an additional 15 minutes.

**Neutralizing:** DO NOT remove the boards or rinse the paste from the hair before neutralizing. Place Paul Brown™ STEP TWO neutralizer into a spray bottle and thoroughly saturate the hair on each board or roller, starting at the scalp spraying to the ends. Start at the back of the nape and move upward and forward. Leave on the hair for 10 minutes. Remove the boards from the scalp gently peeling down and away. Rinse thoroughly (up to 5 minutes). Condition with Paul Brown™ Resurrect, leaving in for 3 to 5 minutes. Rinse again and towel dry. Apply 2-4 drops of Paul Brown™ Diamond Heads and proceed with styling.

After 48-72 hours of stabilizing time the hair should be maintained with Washe Elite, Resurrect and Diamond Heads Cuticle Sealer.

### Hair-at-Rest™

**Preparation:** Wash hair with Washe Elite™ Shampoo and Condition with Resurrect™ for 3-5 minutes.\* Rinse well and towel dry. If hair is extremely porous from previous perms or color, spray generously with Paul Brown™ Treat Elite™.

**Application:** Comb through the hair and section into 4 parts, frontline to nape and from ear to ear. Starting at the nape area, take 3/4 inch sub-partings and apply STEP ONE Crème Texturizer to the section with tint/application brush.

*Virgin Application:* On naturally curly hair apply crème texturizer to a section using a wide toothcomb with medium tension, comb down through the hair to achieve a straighter look. *Re-growth Application:* Apply the crème texturizer to the re-growth area only; pull products through ends during the last five to ten minutes.

*Previously Permed Hair:* Apply the crème texturizer to the permed area, combing gently through.

*Cowlick Redirection:* Apply crème texturizer in the area needed, comb or over direct the treated sections into desired pattern and proceed with processing.

*Roller Set:* Prepare sections for roller, apply Hair-at-Rest™ by combing through for complete distribution and proceed rolling as a roller set or directional wrap, securing with plastic clips.

*Straight Perm Boards:* STEP ONE solution can be buffered with HPFC powder to adhere better to the boards, this will result in a longer processing time.

**Processing:** For previously permed hair or extremely porous hair conditions, check a section in the occipital area after 10 minutes. For naturally curly hair, check a section after 15 minutes. If hair springs back, continue to process and checking in 5-minute increments. PROCESSING TIME SHOULD NOT EXCEED 25 MINUTES INCLUDING THE APPLICATION TIME

Note: when using boards with the buffering HPFC processing time is 30 minutes after the last board.

**Rinse** hair thoroughly for at least 5 minutes. Keep the hair as straight as possible, squeeze excess moisture from the hair and blot dry with a towel.

**Neutralizing:** Apply STEP 2 neutralizer to each section with the same application techniques as used with the processing solution. Thoroughly apply the neutralizer and comb through each section. Allow to process for a full 10 minutes. Rinse 30-5 minutes with warm water. Condition with Alani Sport or Resurrect Conditioner then rinse thoroughly and towel dry. Apply 2-4 drops of Paul Brown™ Diamond Heads and proceed with styling.

After 48-72 hours of stabilizing time the hair should be maintained with Washe Elite, Resurrect and Diamond Heads Cuticle Sealer.

**NOTES:** \*For extremely porous hair Cocktail 1 ounce Resurrect, 1/4 oz. Kukui Nut Oil and 10+ drops Diamond Heads Cuticle Sealer process with a cap under the dryer for 10 – 15 minutes, then rinse thoroughly.

\*\*Apply Barrier to skin to prevent irritation.